



Endeavour® 5 Navigator

FAQ

How do I activate the USB drivers for Endeavour® 5 Navigator 5.4?

Using the “New USB device found Wizard”

When an USB dongle is attached for first time it comes with the “New USB device found Wizard” > **Next** button to take you to the “Files Needed” dialog. It reads: “The file ‘DS2490.sys’ is needed.

1. Select the **Browse** button, and in the *Copy files from* field make sure you have the location c:\WINDOWS\system32\drivers
2. Continue with the default selections **OK**, **Finish** button, etc.

OR

Finding files though *My Computer*

If the “New USB device found Wizard” prompt was cancelled, then

1. Click on the *MY COMPUTER* icon with the Right Mouse Button and select *Properties* > *Hardware* tab > **Device Manager** button.
2. On the “Device Manager” dialog under the *Universal Serial Bus controllers* should be an entry with an icon which has Exclamation mark on a yellow background.
3. Right Mouse Button click on that entry and select *Properties* > *Drivers* tab > **Update Driver** button.
4. Use the **Browse** button to locate the **DS2490.inf** or **DS24902k.inf** files (different for the different Windows systems). They can be located in c:\WINDOWS\system32\drivers or c:\WINDOWS\system32
5. Continue with the default selections to complete the installation.

For more information contact:

 www.hsa.com.au